

The Kite Tuning – upminor version

5	4	3	2	1	0	1	2	3	4	5	6	7	8	9	10	11	12
^M10 439¢ 18/7	P11 498¢ 8/3	^A11 556¢ 11/4	A11 615¢ 20/7	v12 673¢	^12 732¢	m13 790¢ 22/7	~13 849¢ 13/4	M13 907¢ 27/8	Wvm7 966¢ 7/2	W^m7 1024¢ 18/5	WvM7 1083¢ 15/4	W^M7 1141¢ 27/7	WP8 1200¢ 4/1	Wvm9 1259¢ 33/8	W^m9 117¢ 30/7	WvM9 176¢ 22/5	W^M9 234¢ 32/7
^m9 117¢ 15/7	vM9 176¢ 11/5	^M9 234¢ 16/7	m10 293¢ 19/8	~10 351¢ 22/9	M10 410¢ 28/11	v11 468¢ 21/8	^11 527¢ 27/10	d12 585¢ 14/5	vv12 644¢ 26/9	P12 702¢ 3/1	vm13 761¢ 28/9	^m13 820¢ 16/5	vM13 878¢ 10/3	^M13 937¢ 24/7	Wm7 995¢ 32/9	W~7 1054¢ 11/3	WM7 1112¢ 19/5
m7 995¢ 16/9	~7 1054¢ 11/6	M7 1112¢ 19/10	v8 1171¢	^8 1229¢	m9 1288¢ 21/10	~9 146¢ 24/11	M9 205¢ 9/4	vm10 263¢ 7/3	^m10 322¢ 12/5	vM10 380¢ 5/2	^M10 439¢ 18/7	P11 498¢ 8/3	^A11 556¢ 11/4	A11 615¢ 20/7	v12 673¢	^12 732¢	m13 790¢ 22/7
v5 673¢	^5 732¢	m6 790¢ 11/7	~6 849¢ 13/8	M6 907¢ 27/16	vm7 966¢ 7/4	^m7 1024¢ 9/5	vM7 1083¢ 15/8	^M7 1141¢ 27/14	P8 1200¢ 2/1	vm9 1259¢ 33/16	^m9 117¢ 15/7	vM9 176¢ 11/5	^M9 234¢ 16/7	m10 293¢ 19/8	~10 351¢ 22/9	M10 410¢ 28/11	v11 468¢ 21/8
~3 351¢ 11/9	M3 410¢ 14/11	v4 468¢	^4 527¢	d5 585¢ 7/5	vv5 644¢ 13/9	P5 702¢ 3/2	vm6 761¢ 14/9	^m6 820¢ 8/5	vM6 878¢ 5/3	^M6 937¢ 12/7	m7 995¢ 16/9	~7 1054¢ 11/6	M7 1112¢ 19/10	v8 1171¢	^8 1229¢	m9 1288¢ 21/10	~9 146¢ 24/11
^1 29¢	m2 88¢ 21/20	~2 146¢ 12/11	M2 205¢ 9/8	vm3 263¢ 7/6	^m3 322¢ 6/5	vM3 380¢ 5/4	^M3 439¢ 9/7	P4 498¢ 4/3	^A4 556¢ 11/8	A4 615¢ 10/7	v5 673¢	^5 732¢	m6 790¢ 11/7	~6 849¢ 13/8	M6 907¢ 27/16	vm7 966¢ 7/4	^m7 1024¢ 9/5
M6 907¢ 27/32	vm7 966¢ 7/8	^m7 1024¢ 9/10	vM7 1083¢ 15/16	^M7 1141¢ 27/28	P1 0¢ 1/1	vm2 59¢ 28/27	^m2 117¢ 16/15	vM2 176¢ 10/9	^M2 234¢ 8/7	m3 293¢ 19/16	~3 351¢ 11/9	M3 410¢ 14/11	v4 468¢	^4 527¢	d5 585¢ 7/5	vv5 644¢ 13/9	P5 702¢ 3/2

← towards the nut

towards the bridge →

The Kite Tuning – upminor version

open strings	1	2	3	4	5	6	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23	24
^C	vC# Db	^C# wD	D	^D vEb	D# ^Eb	vE	^E	F	^F vGb	F# ^Gb	vG	^G	vG# Ab	^G# wA	A	^A vBb	A# ^Bb	vB	^B wC	C	^C vDb	C# ^Db	vD	^D
A	^A vBb	A# ^Bb	vB	^B wC	C	^C vDb	C# ^Db	vD	^D	vD# Eb	^D# wE	E	^E vF	^F	vF# Gb	^F# wG	G	^G vAb	G# ^Ab	vA	^A	vA# Bb	wB	B
vF# Gb	^F# wG	G	^G vAb	G# ^Ab	vA	^A	vA# Bb	wB	B	^B vC	^C	vC# Db	^C# wD	D	^D vEb	D# ^Eb	vE	^E	F	^F vGb	F# ^Gb	vG	^G	vG# Ab
^D vEb	D# ^Eb	vE	^E	F	^F vGb	F# ^Gb	vG	^G	vG# Ab	^G# wA	A	^A vBb	A# ^Bb	vB	^B wC	C	^C vDb	C# ^Db	vD	^D	vD# Eb	^D# wE	E	^E vF
^B wC	C	^C vDb	C# ^Db	vD	^D	vD# Eb	^D# wE	E	^E vF	^F	vF# Gb	^F# wG	G	^G vAb	G# ^Ab	vA	^A	vA# Bb	wB	B	^B vC	^C Db	vC# wD	^C# wD
G# ^Ab	vA	^A	vA# Bb	wB	B	^B vC	^C	vC# Db	^C# wD	D	^D vEb	D# ^Eb	vE	^E	F	^F vGb	F# ^Gb	vG	^G	vG# Ab	^G# wA	A	^A vBb	A# ^Bb
F	^F vGb	F# ^Gb	vG	^G	vG# Ab	^G# wA	A	^A vBb	A# ^Bb	vB	^B wC	C	^C vDb	C# ^Db	vD	^D	vD# Eb	^D# wE	E	^E vF	^F	vF# Gb	^F# wG	G
vD	^D	vD# Eb	^D# wE	E	^E vF	^F	vF# Gb	^F# wG	G	^G vAb	G# ^Ab	vA	^A	vA# Bb	wB	B	^B vC	^C	vC# Db	^C# wD	D	^D vEb	D# ^Eb	vE

nut → ← towards the bridge →

^C	is tuned to	C	440 hz	+24.4¢	or	446 hz	+0.9¢
A	is tuned to	A	440 hz	+2.4¢	or	441 hz	-1.5¢
vF# / Gb	is tuned to	F# / Gb	440 hz	-19.5¢	or	435 hz	+0.3¢
^D / vEb	is tuned to	D# / Eb	440 hz	-41.5¢	or	430 hz	-1.7¢
^B / wC	is tuned to	B	440 hz	+36.6¢	or	449 hz	+1.5¢
G# / ^Ab	is tuned to	G# / Ab	440 hz	+14.6¢	or	444 hz	-1.0¢
F	is tuned to	F	440 hz	-7.3¢	or	438 hz	+0.6¢
vD	is tuned to	D	440 hz	-29.3¢	or	433 hz	-1.5¢